

i-Vu® Pro v10.0

What's New





Verify that you have the most current version of this document from www.hvacpartners.com, the **Carrier Partner Community** website, or your local Carrier office.

Important changes are listed in **Document revision history** at the end of this document.

Carrier© 2025. All rights reserved.


The content of this guide is furnished for informational use only and is subject to change without notice. Carrier assumes no responsibility or liability for any errors or inaccuracies that may appear in the informational content contained in this guide.

Contents

- What's new in v10.0. 5
 - What's new in the i-Vu® Pro application. 5
 - What's new in Snap. 5
 - What's new in SiteBuilder. 6
 - What's new in ViewBuilder. 6
- Document revision history. 7

What's new in v10.0

What's new in the i-Vu® Pro application

Feature	Improvement
Commissioning equipment	Added All option to quickly enable all points in the control program
Share feature	Replaces the Print button and adds additional options to share i-Vu® Pro content with i-Vu® Pro or non-i-Vu® Pro users
Custom Trend Graph options	<ul style="list-style-type: none"> • Customize trend graph point and line colors • Make some or all lines in a trend graph step graphs • View and print a trend graph in black and white or dashed line style • Show up to 12 data series per trend graph
Multi-graph label alignment	When viewing multiple graphs with different times or increments on the y-axis, i-Vu® Pro automatically aligns these graphs accordingly
Discover BACnet devices by specific values	You can now discover BACnet devices by device instance, address, or name.
ACxelerate Automated Commissioning	Updated interface
Live backup	You can now backup the i-Vu® Pro database as well as all system files into a single .zip bundle , without shutting down the i-Vu® Pro application
Store reports externally	You can now store schedule reports externally
 On-premises only	
Server reconnection behavior	The i-Vu® Pro system no longer returns operators to current tree locations upon server reconnection. For security, you must now log in again if the server restarts.

What's new in Snap

Feature	Improvement
Improved Edit Order	Now integrated into the Reorder menu. Provides enhanced ability to edit and organize items on the Properties page. See the following topics: To reorder items on the Properties page To work with groups To view or edit microblock properties To find a microblock, label, or text in the workspace
Improved zoom capabilities	Use Ctrl + scroll wheel, or the Options menu to zoom the view to 50, 75, 100, 125, 150, or 200%

Feature	Improvement
Productivity tools enhancement	Submenus can now be added to Favorites

What's new in SiteBuilder

Feature	Improvement
Zoom	Zoom feature enabled
Spell check	Spell check integration for Name and Notes fields (Windows only)

What's new in ViewBuilder

Feature	Improvement
Search and replace enhanced	Find and replace names in Objects enhanced with a case-sensitive option and the ability to search inside a selected object
Resizing an image	Holding Shift while resizing an image now maintains the images proportions in the direction dragged
Zoom	Zoom in and out of a graphic view or SVG floorplan Association window using the mouse wheel, keyboard, or interface submenu
Deselect objects	Hold Shift and drag to deselect multiple objects
Show and Hide	F9 now toggles between show and hide so holding down F9 is no longer required
File preview images	File preview images are now larger, and have an option to enlarge the preview even more
Word wrap	Microblock paths now automatically word-wrap the window
Swap Toggle	Swap button allows you to swap the On and Off images for Toggle buttons and Radio buttons.
Toggle between open view files	Press Ctrl+Tab to toggle through open view files
Quick-view object aspects	Object aspect indicator added
Spell check	Spell check integration for Name and Notes fields (Windows only)
Graphics Markup import	Open a Graphics Markup Tool xml file from SiteBuilder.

Document revision history

Important changes to this document are listed below. Minor changes such as typographical or formatting errors are not listed.

Date	Topic	Change description	Code*
11/14/25	What's New in ViewBuilder	Added Zoom	C-PM-RD-E
10/31/25	What's New in ViewBuilder	Removed Graphics Control	C-PM-RD-E

* For internal use only



Carrier ©2025 · Catalog No. 11-808-1213-01 · 11/14/2025