

# i-Vu® Express v10.0

What's New





Verify that you have the most current version of this document from [www.hvacpartners.com](http://www.hvacpartners.com), the **Carrier Partner Community** website, or your local Carrier office.

Important changes are listed in **Document revision history** at the end of this document.

Carrier© 2026. All rights reserved.

The content of this guide is furnished for informational use only and is subject to change without notice. Carrier assumes no responsibility or liability for any errors or inaccuracies that may appear in the informational content contained in this guide.

# Contents

What's new in v10.0. ....	7
What's new in the i-Vu® Express application. ....	7
What's new in Snap. ....	7

## What's new in v10.0

---

### What's new in the i-Vu® Express application

Feature	Improvement
Commissioning equipment	Added <b>All</b> option to quickly enable all points in the control program
<b>Share</b> feature	<b>Replaces</b> the <b>Print</b> button and adds additional options
Custom Trend Graph options	Customize trend graph point and line colors Make some or all lines in a trend graph step graphs View and print a trend graph in black and white or dashed line style
Multi-graph label alignment	When viewing multiple graphs with different times or increments on the y-axis, i-Vu® automatically aligns these graphs accordingly
Discover BACnet devices by specific values	You can now discover BACnet devices by device instance, address, or name.
Operator password	Administrator password is now required to change the operator password.

### What's new in Snap

Feature	Improvement
Improved zoom capabilities	Use <b>Ctrl</b> + scroll wheel, or the <b>Options</b> menu to zoom the view to 50, 75, 100, 125, 150, or 200%



Carrier ©2026 · Catalog No. 11-808-1208-01 · 1/27/2026